



EasyConnect User Guide

Revision History

Version	Description	Date
V1.0.0	Initial release.	Jan 19, 2021
V1.0.1	Updated the support firmware version of HR1580-BT and HR5280-BT	Jun 22, 2021

Table of Content


About EasyConnect.....	1
How to Use EasyConnect.....	1
Supported Products.....	3
Supported Operating System of Host.....	3

About EasyConnect


EasyConnect is a connection application developed by Newland Auto-ID Technology Co., Ltd. It can be directly installed on mobile phones, PDAs and other Android mobile devices. The bluetooth scanners can be directly connected to the mobile device by using this application and transmit the data to the Android devices in real time.

How to Use EasyConnect

1. Download [EasyConnect](#) installation package and run it after installation.



2. Allow EasyConnect to access this device's location.



3. Scan the below barcodes to set the scanner in Bluetooth HID mode and clear pairing info on scanner.



@SETUPE1

Enter Setup



@WLSCLP

Clear Pairing Information of Scanner



@INTERF10


Bluetooth HID Mode



@SETUPE0

Exit Setup

4. Scan the pairing barcode on the EasyConnect and then connection completed.



Once a scanner and an Android device is paired, no repairing is required unless the pairing information is cleaned.

Supported Products

Supported products are listed as below

HR15-BT (Firmware version HR15-BT_V1.01.017 or later is required)

HR22-BT (Firmware version HR22-BT_V1.01.006 or later is required)

HR32-BT (Firmware version HR32-BT_V1.01.021 or later is required)

HR52-BT (Firmware version HR52-BT_V1.02.003 or later is required)

Supported Operating System of Host

Android 6 later is required.

Newland Auto-ID Tech. Co., Ltd. (Headquarter)

Add: No.1, Rujiang West Rd., Mawei, Fuzhou, Fujian 350001, China

Tel: +86 (0) 591 8397 9500

Fax: +86 (0) 591 8397 9216

E-mail: info@nlscan.com

Web: www.newlandaidc.com

Newland APAC

Newland Taiwan Inc.

Add: 7F-6, No. 268, Liancheng Rd., Jhonghe Dist. 235,

New Taipei City, Taiwan

Tel: +886 2 7731 5388

Fax: +886 2 7731 5389

Email: info@newland-id.com.tw

Web: www.newland-id.com.tw

Newland Korea

Add: Biz. Center Best-one, Jang-eun Medical Plaza 6F, Bojeong-dong
1261-4, Kihung-gu, Yongin-City, Kyunggi-do, South Korea

Tel: +82 10 8990 4838

Fax: +82 70 4369 0009

Email: info@nlscan.com

Web: www.newlandaidc.com/kor/

Newland Japan

Tel: +886 2 7731 5388 ext. 71

Email: info@nlscan.com

Web: www.newlandaidc.com/jp/

Newland India

Add: 814, Tower B, NOIDA ONE business park B-8, Sector 62, Noida,
Uttar Pradesh-201301

Tel: +91 120 7964266

Email: info@nlscan.com

Web: www.newlandaidc.com

Newland EMEA

Newland Europe BV

Add: Rolweg 25, 4104 AV Culemborg, The Netherlands

Tel: +31 (0) 345 87 00 33

Fax: +31 (0) 345 87 00 39

Email: sales@newland-id.com

Tech Support: tech-support@newland-id.com

Web: www.newland-id.com

Newland NALA

Newland North America Inc.

Add: 46559 Fremont Blvd., Fremont, CA 94538, USA

Tel: +1 510 490 3888

Fax: +1 510 490 3887

Email: info@nlscan.com

Web: www.newlandamerica.com

Newland Latin America

Tel: +1 (239) 598 0068

Fax: +1 (239) 280 1238

Email: info@newlandla.com

Web: www.newlandamerica.com